

Quark 5 and 6 Color Management Settings

Setting up color management in Quark 5 or 6 is an identical process.


Before You Start: It is imperative that all Quark documents be closed while setting up the color settings or the settings will only be applied to the document that is open.

Step One: Download and install the Taylor ICC profile.

See Photoshop downloads (<http://www.taylorpub.com/techsupport/qDownloads.aspx>). Download the Windows or Mac package with settings. Unpackage folder and install settings and profile.


Step Two: Open your Quark Preferences window.

Choose Quark CMS (color management system) and select the correct ICC profiles and settings as indicated below on the RGB tab.



Step Three: Select the CMYK tab


Select the correct ICC profiles and settings as indicated below on the CMYK tab. The hexachrome settings are not used.



Your color settings are now set up correctly.

If the TPC_Std_CMYK.icc is not available in the profile list to select, copy it onto your hard drive and proceed to step four. The profile manager will be grayed out unless color management is active.

Step Four: Select the Profile Manager from your Utilities Drop down menu.



1. Choose the select or browse button and navigate to the folder you copied the ICC profile into and choose select.
2. Select the update button and the Taylor ICC profile will be added to the list in the profile manager.
3. Now repeat steps three and four choosing the Taylor ICC profile in the appropriate fields.

Note: All profiles except the two that are needed can be turned off in the profile manager making it harder for your color settings to be altered accidentally.